## Sheet1

API version	1.01
Date	05.03.17
Status	Open

## implemented responses

200, 404. 423, 400, 405, 408

Parameter ID	uri	POST	GET	DELETE	ĺ	description
	/Paramerer{xxx}	Х	Х	Х		accesses parameter of given number {xxx}. Expect 404, 423
xxx	/ISM010_{xxx}	X	х		int	ModbusRegister of ISM010 xxx provides address of register. Should manage trailing zeros, expect 423 return code in :http://www.restpatterns.org/HTTP_Status_Codes/423Locked
	/Time/Time	x	X		int	current time in unix time format Unix time (also known as POSIX time or epoch time) is a system for describing instants in time, defined as the number of seconds that have elapsed since 00:00:00 Coordinated Universal Time (UTC), Thursday, 1 January 1970,[1]cite_ref-2cite_ref-2[note 1] not counting leap seconds.[1]cite_ref-3cite_ref-3[2]cite_ref-4cite_ref-4[note 2] https://en.wikipedia.org/wiki/Unix_time
1001	/Time/SystemStartTime		Х		int	time of last power on in unix time(see details of /Time/Time)
1002	/Time/SystemUptime		Х		int	number of seconds since last powe on
1100	/Runtime/LastIgnition		Х		int	time of last successful ignition in unix time (see /time/Time)
1101	/Runtime/StateUptime		Х		int	number of seconds since last change of phase
1102	/Runtime/State		Х		str	name of current state (string)
1200	/Errors/LastErrorTime		Х		int	time when the last error appeared in unix time
1201	/Errors/LastError		Х		int	last error (string)
1202	P/Errors/ErrorList		Х	Х	[[int, int,str]]	error log file. Delete clears out error list array of [time, error code, error name]
1300	/Properties/ID		Х		str	identification sting unique for each device
1301	/Properties/Firmware		Х		str	firmware version of ISWiFi
1302	Properties/Hardware		Х		str	hardware version of ISWiFi
1303	/Properties/LastChange		Х		[int, str, str,str]	time of last change of parameters in unix time, parameter name, old and new value [time,name, old val, new val]
1304	/Properties/Changes		Х	Х	[[int, str, str,str]]	parameter change list
1305	/Properties/Log		Х	Х	[[int, str]]	log file, delete clears log, array of [time, log entry]
1306	/Properties/PermLog		Х		[[int, str]]	Non-volatile log file, array of [time, log entry]
						dump of all current settings, array of [name, value] (does not return ISM0-10
1307	/Properties/Settings		Х		[[str. Str]]	registers)
1308	Properties/UART1	Х	Х		[int, int, str, int]	uartmode in form 96008N1

## Sheet1

1309	/Properties/UART2	Х	Х	[int, int, str, int]	uartmode in form 96008N1
1310	/Properties/APIversion		Χ	str	version of API
1400	/Querry/Interval	Х	Χ	int	time in ms between requests sent to ISM010
					value in % defining sensitivity range. When parameter from querry changes more
1401	/Querry/SensRange	Х	Χ	int	that this value from stored one, new entry is saved
	/Modbus/Type	Χ	Х	str	Type of external modbus communication: rtu/ascii case insensitive
1501	/Modbus/Address	Х	Χ	inr	modbus slave address of device
					time in ms after routing a modbus command that will cause 0x0B Gateway Target
1502	/Modbus/Delay	Х	Х	int	Device Failed to Respond timeout error if no reply received
	/TempController/Temperature_n		Х	Int0.1	current temperature of n-th sensor seen by controller (int 0.1degC)
11 /	/TempController/Output_n		Х	bool	current state of regulator output (bool)
	/TempController/Setpoint_n	Х	Х	Int0.1	current setpoint (int 0.1degC)
1603+((n-1)*10)	/TempController/Hysteresis_n	Х	Χ	Int0.1	hysteresis of controller (int 0.1degC)
999	/ISM010_all		Х	[[int, int]]	get newest settings from ISM0-10 , [register address, value]
998	/ISM010_available		Χ	bool	true if there was recent successful communication with ISM, 0 otherwise
					should restart ISM010 if proper code is sent. All requests for ISM parameters
2000	/ISM010_restart	Х		int	should result with 423 error code until restart is done, set ISM010available=0